

9.6.2 How to use the User Log function

1. In the Editor area of the **RL** page, use the *SetUserLogSize* instruction to specify the maximum size of the file to be saved to the USB drive, the *print* instruction to specify the data to be retrieved, and the *SetUserLogToUSB* instruction to specify the filename.

```
A = 256  
  
SetUserLogSize(A)  
  
for i = 1,30000 do  
    print(i.." , 1234567890")  
end  
  
SetUserLogToUSB("123.txt")
```

2. To save the User Log file to the PC, go to the **RL User Log** tab in the **Info** page.

